

How to Install fS Software Win 7

USER GUIDE #02-W7



How to Install fotoShout Windows 7




[To Install fotoShout in a Windows 8.x System - see users guide #2-W8](#)


Do Not Install fotoShout Without Reviewing This Guide First

Be sure to view "Tips" at bottom of guide

1. Login into the Apple App store using your iPad or iPad mini, download & install fotoShout. *(If you haven't already done so)*
2. Go <http://fotoshout.com/> (Computers must be running Windows 7, Windows 8 or 8.1 – 64 bit operating system).
 - a. login to fotoShout at <http://fotoshout.com/>
 - b. At the top of page click on "**Download.**" Save the zip file to your computer.
 - i. A dialog box **may pop** up after the download completes, **usually in the lower left corner** of your computer screen stating, "**fotoShout Client_1.3_Zip is not commonly downloaded and could be dangerous.**" Click on the **Down Triangle Icon** next to the word "**Discard**" select "**Keep.**" Click "Keep."
 - c. Unzip file; (right click file, select "Extract All"). After extraction you will be viewing 2 files.
 - i. fotoshout _1.3_WIN64.exe
 - ii. IIS.bat file
 - d. This is **IMPORTANT** –
 - i. Disable your Firewall, and Anti-virus during installation and setup. We have found some antivirus software cause issues **during** setup.
 - ii. **Right click** the **IIS.bat** file, a popup menu will open. Select "**Run As Administrator.**" The file will install, follow the prompts, it takes a minute or two. When complete text within a Black Dialog box will display "**Press Any Key To Continue**"
 - iii. After IIS is installed **Right Click** the "**fotoShout _1.3WIN64.exe**" file. Select "**Run as Administrator**" A dialog box will pop up – "*fotoShout client requires the following items to be installed on your computer.*" **Click the Install button.** *(Be patient this can take a while. fotoShout is installing your database)*
 - iv. When the text appears "Success," close the dialog box.
 - v. Reboot Computer
 - e. This portion of setup is **unique to fotoShout Beta**, and needs to be completed only once on each event computer.
 - i. Go to Windows Explorer. Type in "**%programdata%\fotoshout**" *(without the quotes)* press **enter** on the keyboard. Open the "SyncSettings.config" file **(see images below)** When Clicking on "**Syncsettings.config**" if you have **Never** viewed this type of file before, Windows will ask you what program you would like to use to read this file. Right Click on "syncsettings.config," Click on "**More Options**". Select and click on "**Notepad**". **Syncsettings.config** will now open.
 - ii. Scroll down to **password** and **user name**. Replace the entered e-mail address with your **e-mail address**. Replace the word password with your actual "**password.**"
 - iii. Click on File, then Click "**SAVE**"
 - iv. Go to Windows Explorer, type in- "**%windir%\system32\services.msc**" *(without the quotes)* - press enter. A dialog box will open. Scroll down to "**fotoShout Sync Service.**" Left click on "**fotoShout Sync Service**" to highlight. Click **Start** the Service. **(see images below)** Please note; Part of the message in the highlighted area

will display “Started” and “Automatic,” but you still need to click “Start Service” the very first time you install fotoShout.





fotoShout software setup is complete



TIPS

When Clicking on ***"Syncsettings.config"*** if you have **Never** viewed this type of file before, Windows will ask you what program you would like to use to read this file. Right Click on "syncsettings.config," Click on **"More Options"**. Select and click on **"Notepad"**. **Syncsettings.config** will now open.